

Re: [SLE] Simply file sharing

Source: <http://linux.derkeiler.com/Mailing-Lists/SuSE/2004-01/2930.html>

From: jaska (*jaska_at_ritari.fi*)

Date: 01/22/04

To: suse-linux-e@suse.com

Date: Thu, 22 Jan 2004 09:59:23 +0200

Hi

Not sure what You need, but a "basic" sharing could be for example this:

Open a terminal, and become root (in terminal give command "sux", and give the root-password")

Make a directory /home/public (mkdir /home/public).

Give it rights "chmod u+rwx,g+rwx,o+rwx /home/public"

Change the owner "chown nobody:nogroup /home/public"

Put this into /etc/samba/smb.conf:

```
[public]
  comment = The share
  path = /home/public
  force user = nobody
  read only = No
  create mask = 0666
  directory mask = 0777
  guest only = Yes
  guest ok = Yes
```

And restart samba "rcsamba restart" (or rcsmb restart if You are running older SuSE version)

Jaska.

admin kirjoitti viestissään (lähetysaika Torstai 22. Tammikuuta 2004 08:15):

```
> I have a simply question. I've installed the samba, and I see the Linux
> machine in the windows network, but I can't make a file sharing. How can I
> do this?
```

--

Check the headers for your unsubscription address

For additional commands send e-mail to suse-linux-e-help@suse.com

Re: [SLE] Simply file sharing

SuSE: Re: [SLE] Simply file sharing

Also check the archives at <http://lists.suse.com>
Please read the FAQs: suse-linux-e-faq@suse.com