

[PATCH 517] M68k: Disable SERIO_I8042, except on Q40/Q60

Source: <http://linux.derkeiler.com/Mailing-Lists/Kernel/2004-10/10240.html>

From: Geert Uytterhoeven (geert_at_linux-m68k.org)

Date: 10/31/04

Date: Sun, 31 Oct 2004 11:03:41 +0100

To: Linus Torvalds <torvalds@osdl.org>, Andrew Morton <akpm@osdl.org>, Vojtech Pavlik <vojtech@su>

M68k: Disable SERIO_I8042, except on Q40/Q60

Signed-off-by: Geert Uytterhoeven <geert@linux-m68k.org>

```
--- linux-2.6.10-rc1/drivers/input/serio/Kconfig 2004-09-30 12:53:37.000000000 +0200
+++ linux-m68k-2.6.10-rc1/drivers/input/serio/Kconfig 2004-10-27 23:16:43.000000000 +0200
@@ -20,7 +20,7 @@ config SERIO_I8042
     tristate "i8042 PC Keyboard controller" if EMBEDDED || !X86
     default y
     select SERIO
- depends on !PARISC && (!ARM || ARCH_SHARK || FOOTBRIDGE_HOST)
+ depends on !PARISC && (!ARM || ARCH_SHARK || FOOTBRIDGE_HOST) && (!M68K || Q40)
---help---
     i8042 is the chip over which the standard AT keyboard and PS/2
     mouse are connected to the computer. If you use these devices,
```

Gr{oetje,eeting}s,

Geert

--

Geert Uytterhoeven -- There's lots of Linux beyond ia32 -- geert@linux-m68k.org
In personal conversations with technical people, I call myself a hacker. But
when I'm talking to journalists I just say "programmer" or something like that.

-- Linus Torvalds

-

To unsubscribe from this list: send the line "unsubscribe linux-kernel" in
the body of a message to majordomo@vger.kernel.org

More majordomo info at <http://vger.kernel.org/majordomo-info.html>

Please read the FAQ at <http://www.tux.org/lkml/>